

ETHERNET PROTOCOL

LD-MRS Laser Scanner



Table of Content

- 1. Introduction 2
- 2. General information 2
 - 2.1. Ethernet configuration 2
 - 2.2. Data encoding 2
 - 2.3. Data header 3
- 3. Scan data 4
- 4. Errors and warnings 6
- 5.

1. Introduction

This document describes how data is received and transmitted from respectively to the LD - MRS via the Ethernet connection. Addressed systems are LD - MRS 400001 and LD - MRS 400102 sensors or applications using the software versions (e.g. LD - MRS View).

2. Ethernet configuration

The LD - MRS uses default ethernet configurations until changed by the user.

| Default ethernet settings | |
|---------------------------|---------------|
| IP address | 192.168.0.1 |
| Subnet mask | 255.255.255.0 |
| Port | 12002 |

3. Data encoding

 See the data type description if little or big endian byte order is used!

Timestamps represent the time encoded in 8 bytes. The higher 4 bytes are the number of seconds. The lower 4 bytes represent the fractional seconds with a resolution of 2^{-32} s. These 2 values must be interpreted as two unsigned 32 bit values.

4. Data header

Each message always starts with a data header. To resync just search for the magic word.

| Data header | | | | | |
|-----------------|--------|----------------------------|--------|------------|---|
| Bytes | Offset | Field | Type | Byte order | Description |
| 4 | 0 | Magic word (0xAFFEC0C2) | uint32 | Big endian | The magic word is used for searching messages and to distinguish between different versions |
| 4 | 4 | Size of previous messages | uint32 | Big endian | Helps to navigate backwards through a file. Unused in live data |
| 4 | 8 | Size of this message | uint32 | Big endian | Helps to read the message data. Size of message content without this header |
| 1 | 12 | Reserved | uint8 | Big endian | – |
| 1 | 13 | Device ID | uint8 | Big endian | ID of the connected device. Unused in data received directly from scanner |
| 2 | 14 | Data type | uint16 | Big endian | Specifies the data type within message |
| 8 | 16 | Timestamp | uint64 | Big endian | Time when this message was created |
| Total: 24 bytes | | | | | |

5. Scan data

Each scan data block starts with a header followed by the scan point list. For angle information the unit angle ticks is used. A LD - MRS uses 11520 ticks per rotation. Thus the angular resolution $\frac{1}{32^\circ}$. This value is needed to convert angle ticks: $angle = 2\pi \cdot \frac{angle\ ticks}{angle\ ticks\ per\ rotation}$.

Angles are given in the ISO 8855 / DIN 70000 scanner coordinate system.

| Scan header (data type: 0x2202) | | | | | |
|---------------------------------|--------|--------------------------|--------|---------------|---|
| Bytes | Offset | Field | Type | Byte order | Description |
| 2 | 0 | Scan number | uint16 | Little endian | The number of this scan. The number will be increased from scan to scan |
| 2 | 2 | Scanner status | uint16 | Little endian | 0x0007 : reserved 0x0008 : set frequency reached 0x0010 : external sync signal 0x0020 : sync ok 0x0040 : sync master 0xFF80 : reserved |
| 2 | 4 | Sync phase offset | uint16 | Little endian | Phase difference (conversion factor 409.6 ns) between sync signal and scanner mirror crossing the synchronization angle |
| 8 | 6 | Scan start time | uint64 | Little endian | Time when first measurement was done |
| 8 | 14 | Scan end time | uint64 | Little endian | Time when first measurement was done |
| 2 | 22 | Angle ticks per rotation | uint16 | Little endian | Number of angle ticks per rotation |

| | | | | | |
|-----------------|----|-------------|--------|---------------|---|
| 2 | 24 | Start angle | int16 | Little endian | Start angle in angle ticks of this scan |
| 2 | 26 | End angle | int16 | Little endian | End angle in angle ticks of this scan |
| 2 | 28 | Scan points | uint16 | Little endian | Number of scan point transmitted in this scan |
| 2 | 30 | Reserved | int16 | Little endian | – |
| 2 | 32 | Reserved | int16 | Little endian | – |
| 2 | 34 | Reserved | int16 | Little endian | – |
| 2 | 36 | Reserved | int16 | Little endian | – |
| 2 | 38 | Reserved | int16 | Little endian | – |
| 2 | 40 | Reserved | int16 | Little endian | – |
| 2 | 42 | Reserved | uint16 | Little endian | – |
| Total: 44 bytes | | | | | |

6. Scan point

An array of points follows the scan header. See number of scan points in the scan header description above.

| Scan point | | | | | |
|-----------------|--------|------------------|--------|---------------|---|
| Bytes | Offset | Field | Type | Byte order | Description |
| 1 | 0 | Echo and layer | uint8 | Little endian | Bits 0 – 3: scan layer of point Bits 4 – 7: echo number of point (both zero – based) |
| 1 | 1 | Flags | uint8 | Little endian | 0x01: transparent point 0x02: clutter (atmospheric) 0x08: dirt 0xF: reserved |
| 2 | 2 | Horizontal angle | int16 | Little endian | Angle of point in angle ticks in the scanner coordinate system |
| 2 | 4 | Radial distance | uint16 | Little endian | Distance of point in angle ticks in the scanner coordinate system |
| 2 | 6 | Echo pulse width | uint16 | Little endian | Detected width of this echo pulse in cm |
| 2 | 8 | Reserved | uint16 | Little endian | – |
| Total: 10 bytes | | | | | |

7. Errors and warnings

As soon LD - MRS detects an error or wants to emit a warning, this message is sent. Errors and warnings bits are reset after sending this message. This message will be sent periodically as long as errors or warnings persist.

| Errors and warnings (data type: 0x2030) | | | | | |
|---|--------|------------------|--------|---------------|---|
| Bytes | Offset | Field | Type | Byte order | Description |
| 2 | 0 | Error register 1 | uint16 | Little endian | Bits 0 – 1: contact support Bit 2: scan buffer transmitted incompletely, decrease scan resolution, frequency or range; contact support Bit 3: scan buffer overflow, decrease scan resolution, frequency, range, contact support Bits 4 – 13: contact support Bits 5 – 7: reserved Bit 9: APD over temperature, provide cooling Bit 8: APD under temperature, provide heating Bits 8 – 9: APD temperature sensor defect, contact support Bits 14 – 15: reserved |

| | | | | | |
|---|---|--------------------|--------|---------------|---|
| 2 | 2 | Error register 2 | uint16 | Little endian | Bits 0 – 3: contact support Bit 4: incorrect configuration data, load correct values Bit 5: configuration contains incorrect parameters, load correct values Bit 6: data processing timeout, decrease scan resolution or frequency Bit 7: contact support Bit 8 – 15: reserved |
| 2 | 4 | Warning register 1 | uint16 | Little endian | Bit 0: internal communication error Bits 1 – 2: internal warning Bit 3: temperature very low Bit 4: temperature very high Bits 5 - 6: internal warning Bit 7: synchronization error, check synchronization and scan frequency Bits 8 – 15: reserved |

| | | | | | |
|-----------------|----|--------------------|--------|---------------|---|
| 2 | 6 | Warning register 2 | uint16 | Little endian | Bit 0: reserved Bit 1: Ethernet interface blocked, check Ethernet connection Bit 2: reserved Bit 3: contact support Bit 4: error receiving Ethernet data, check Ethernet connection or data Bit 5: incorrect or forbidden command received, check command Bit 6: memory access failure, restart scanner, contact support Bits 7 – 15: reserved |
| 2 | 8 | Reserved | uint16 | Little endian | – |
| 2 | 10 | Reserved | uint16 | Little endian | – |
| 2 | 12 | Reserved | uint16 | Little endian | – |
| 2 | 14 | Reserved | uint16 | Little endian | – |
| Total: 16 bytes | | | | | |

8. Command interface

Commands are used for configuring scanner parameters. Data structures below shows how messages are formed and transmitted.